## Command format

LC – Local Controller

MC – Main Controller

1	1	0	1	•••	2	;
Command			Data			End symbol

## Begin symbol:

0 – IP

1 – Sea temp

2 – Air temp

3 – UNIX time

\$ - system command (brightness)

1 – day brightness

2 – night brightness

## **Command**

Command				
<mark>11</mark>	First initialization. Set number of LC in system = 1 and set address of first			
	controller.			
	F.e. \$000110101; 1 LC in system with address = 101			
<mark>02</mark>	Set address for the next LC			
	F.e. \$000020102; Set second controller with address 102			
<mark>01</mark>	Send data			
	F.e. \$101011234; Send data "1234" to LC with address 101			
<mark>12</mark>	Set brightness (1-255)			
	F.e. \$101120255;			
<mark>77</mark>	Test data			
	F.e. \$000774321;			